


# CONFERO

## RELEASE NOTES



## COPYRIGHT STATEMENT

No part of this publication or documentation accompanying this product may be reproduced in any form or by any means or used to make any derivative such as translation, transformation, or adaptation without the prior written permission of the publisher, except in case of brief quotations embodied in critical articles or reviews. Contents are subject to change without prior notice.

Copyright © 2020 by Televic Conference NV. All rights reserved.

The authors of this document have made every effort in the preparation of this book to ensure the accuracy of the information. However, the information in this manual is supplied without warranty, either express or implied. Neither the authors, Televic Conference NV, nor its dealers or distributors will be held liable for any damages caused or alleged to be caused either directly or indirectly by this book.

## TRADEMARKS

All terms mentioned in this manual that are known to be trademarks or service marks have been appropriately capitalized. Televic NV cannot attest to the accuracy of this information. Use of a term in this book should not be regarded as affecting the validity of any trademark or service mark.

# DOCUMENT HISTORY

Version	Date	Description
0.1	2020-05-28	Release notes version 7.0.12
0.2	2020-06-11	Release notes version 7.0.15

# CONTENTS

Document history .....	3
IMPORTANT COMPATIBILITY NOTICE .....	5
CONFERO 7.0.15.....	6
CONFERO 7.0.12.....	7

## RELEASE NOTES

### IMPORTANT COMPATIBILITY NOTICE



When updating your Plixus system to CRP 7.0, CoCon is not yet supported. To use CoCon with your Plixus system, use a previous CRP 6.X

# CONFERO 7.0.15

## FIXED ISSUES

- Fixed an issue with voting without optional voting question (UNIMM-4093)
- Fixed an issue where adding a delegate on a seat could fail when starting an empty meeting and no delegates have been created (UNIMM-4086)
- Fixed an issue where clearing the speaker list also clears the request list (UNIMM-4074)
- Fixed an issue where in rare occasion, updating a Plixus MME to CRP 7.0 could fail (UNIMM-4070)
- Fixed an issue with starting a vote without the optional voting question (UNIMM-4093)

## KNOWN LIMITATIONS

- No support yet for uniCOS and uniBOX, Plixus Nameplate
- No support yet for CoCon
- No support yet for DANTE-on-seat
- No support yet for Intercom
- No support yet for iOS or Android tablet browsers
- No support yet for the reply functionality
- No API control yet for Confero 360 features (Plixus Core REST API is supported)
- When upgrading the Plixus engine from a previous version, the device and audio and interpreter configurations are reset
- When using Confidea FLEX in dual delegate mode, the device cannot be used to read badge ID's in the meeting template configuration
- When using Confidea FLEX in dual delegate mode, the diagnostics speaker test cannot be performed on those units (UNIMM-4067)
- After stopping a meeting, the last meeting remains in the current meeting tab until you refresh the page (UNIMM-4001)
- After importing a configuration, files are not copied to the correct location (UNIMM-4095)
- In rare occasions, Confidea FLEX units are not marked as offline, although they are not connected to the Plixus engine (UNIMM-4096)

# CONFERO 7.0.12

## WHAT'S NEW

- Log in as technician
- Start a quick setup wizard to configure the system
- Add quick links to the technician dashboard
- Change web UI to a dark layout
- Change the login screen background
- Support for 28 interface languages
- Improved update mechanism ( select one or more product families to update rather than updating the complete system)
- Automatic device detection
- Automatic DANTE interface detection
- Automatically create booths and combine desks during seat reordering
- Assign Confidea FLEX licenses with the web interface in addition to on the unit itself
- Support for **Confero 360 (a Confero 360 license is required to activate these features)**
  - Log in as operator, chairperson or signage with optional password protection
  - Edit your dashboard layout (vertical or horizontal orientation)
  - Create a room layout and easy seat number reordering
  - Create a meeting template with delegates
  - Add RFID badge ID's to delegates
  - Microphone control with room layout, speaker list, request list
  - Rotate the room layout
  - Reorder requests in the request list
  - Interpretation monitor to see active channels and booths
  - Start voting (yes/no or yes, no abstain, public or secret)
  - See discussion or voting results when logged in as signage
  - Consult up to 50 meeting reports stored on the central unit
  - Change default microphone sensitivity or temporarily change the sensitivity in a meeting

## FIXED ISSUES

- Improved AUX IN gain settings notation to: -24dB to OFF (UNIMM-2110)
- Fixed an issue with the Plixus engine's web server not being available when no devices are connected (UNIMM-3681)
- Fixed an issue with the Plixus Core API GetAllUnits call (UNIMM-3833)
- Fixed an issue that website is accessible even when there are no units connected (UNIMM-3681)

## KNOWN LIMITATIONS

- No support yet for uniCOS and uniBOX, Plixus Nameplate
- No support yet for CoCon
- No support yet for DANTE-on-seat
- No support yet for Intercom
- No support yet for iOS or Android tablet browsers
- No support yet for the reply functionality
- No API control yet for Confero 360 features (Plixus Core REST API is supported)
- When upgrading the Plixus engine from a previous version, the device and audio and interpreter configurations are reset
- When using Confidea FLEX in dual delegate mode, the device cannot be used to read badge ID's in the meeting template configuration
- When using Confidea FLEX in dual delegate mode, the diagnostics speaker test cannot be performed on those units (UNIMM-4067)
- After stopping a meeting, the last meeting remains in the current meeting tab until you refresh the page (UNIMM-4001)

